

$M(t\bar{t})$ [GeV]	$\frac{d\sigma}{dM(t\bar{t})}$ [fb GeV $^{-1}$]	$M(t\bar{t})$ [GeV]	$\frac{d\sigma}{dM(t\bar{t})}$ [fb GeV $^{-1}$]
Additional jets: 0			
300–360	$43.7 \pm 0.6 \pm 4.9$	680–800	$31.4 \pm 0.3 \pm 1.6$
360–430	$109.8 \pm 0.7 \pm 5.8$	800–1000	$14.27 \pm 0.17 \pm 0.91$
430–500	$104.2 \pm 0.7 \pm 6.0$	1000–1200	$5.24 \pm 0.12 \pm 0.50$
500–580	$80.9 \pm 0.5 \pm 4.4$	1200–2000	$0.989 \pm 0.034 \pm 0.086$
580–680	$53.8 \pm 0.4 \pm 3.0$		—
Additional jets: 1			
300–360	$20.7 \pm 0.3 \pm 2.2$	680–800	$15.6 \pm 0.2 \pm 1.0$
360–430	$59.7 \pm 0.5 \pm 3.9$	800–1000	$6.79 \pm 0.11 \pm 0.46$
430–500	$57.3 \pm 0.4 \pm 4.1$	1000–1200	$2.43 \pm 0.07 \pm 0.25$
500–580	$42.9 \pm 0.3 \pm 2.8$	1200–2000	$0.385 \pm 0.017 \pm 0.043$
580–680	$27.9 \pm 0.3 \pm 2.0$		—
Additional jets: 2			
300–360	$6.85 \pm 0.14 \pm 0.55$	680–800	$5.60 \pm 0.10 \pm 0.56$
360–430	$22.3 \pm 0.3 \pm 1.7$	800–1000	$2.44 \pm 0.06 \pm 0.20$
430–500	$21.2 \pm 0.2 \pm 2.1$	1000–1200	$0.85 \pm 0.04 \pm 0.10$
500–580	$15.9 \pm 0.2 \pm 1.4$	1200–2000	$0.135 \pm 0.009 \pm 0.019$
580–680	$10.06 \pm 0.14 \pm 0.95$		—
Additional jets: ≥ 3			
300–360	$2.52 \pm 0.08 \pm 0.33$	680–800	$2.49 \pm 0.06 \pm 0.36$
360–430	$9.5 \pm 0.2 \pm 1.0$	800–1000	$1.14 \pm 0.04 \pm 0.19$
430–500	$9.7 \pm 0.1 \pm 1.1$	1000–1200	$0.418 \pm 0.025 \pm 0.057$
500–580	$7.14 \pm 0.12 \pm 0.77$	1200–2000	$0.065 \pm 0.006 \pm 0.019$
580–680	$4.58 \pm 0.09 \pm 0.54$		—